



C#_SDK_Quick Start

Routine Description



名称	修改日期	类型	大小
obj	3/4/2024 下午4:47	文件夹	
Properties	3/4/2024 下午4:47	文件夹	
WitSdk	3/4/2024 下午4:47	文件夹	
.gitignore	3/4/2024 下午3:35	Git Ignore 源文件	5 KB
App.config	3/4/2024 下午3:35	Configuration 源...	1 KB
Form1.cs	3/4/2024 下午4:57	C# Source File	23 KB
Form1.Designer.cs	3/4/2024 下午4:57	C# Source File	10 KB
Form1.resx	3/4/2024 下午4:57	Microsoft .NET ...	23 KB
Form1.zh-CN.resx	3/4/2024 下午4:57	Microsoft .NET ...	11 KB
Program.cs	3/4/2024 下午3:35	C# Source File	1 KB
README.md	3/4/2024 下午4:47	Markdown 源文件	7 KB
Wit.Example_BWT901BLE.csproj	3/4/2024 下午4:38	C# Project File	10 KB
Wit.Example_BWT901BLE.csproj.us...	3/4/2024 下午4:17	Per-User Project...	1 KB
Wit.Example_BWT901BLE.sln	3/4/2024 下午3:35	Visual Studio Sol...	2 KB

Directions:

Install Visual Studio 2019 or higher on your computer and select the sln solution to enter

Download the example

Go to the link below to download the example

https://github.com/WITMOTION/WitBluetooth_BWT901BLE5_0/tree/main/Windows_C%23

Noun introduction

Bluetooth 5.0 protocol: This is the protocol used by Witt smart Bluetooth 5.0 sensors. The protocol stipulates that the sensor returns data packets starting with 55, and the host computer sends data packets starting with FF AA.


Routine Introduction

This example introduces how to use C# to develop a host computer to connect to a Bluetooth 5.0 protocol sensor, receive sensor data and communicate with the sensor;

Please read the relevant sensor manual before viewing this example to understand the protocol used by the sensor and the basic functions of the sensor.

Routine Directory

The routine project directory is as follows



Folder Description:

_Dll: The sample program Bluetooth connection dependency library. You need to import the files in it into the project reference.

ble5: BWT901BLE5.0 device model

WitSdk: Wit sample program dependency package

Form1: sample program entry, main interface, this sample only has this interface

Open Search

The BWT901BLE object represents the BWT901BLE device in the program. You can use it to communicate with the device. When searching for a device, call `bluetoothManager.StartScan()` to start the search. When opening a device, you need to specify the Bluetooth address of the Bluetooth sensor. After specifying it, call the `BWT901BLE.Open()` method.

```
/// <summary>
/// Start searching
/// </summary>
/// <param name="sender"></param>
/// <param name="e"></param>
private void startScanButton_Click(object sender, EventArgs e)
{
    // Clear the found device
    FoundDeviceDict.Clear();

    // Close the previously opened device
    for (int i = 0; i < FoundDeviceDict.Count; i++)
    {
        var keyValue = FoundDeviceDict.ElementAt(i);
        BWT901BLE bWT901BLE = keyValue.Value;
        bWT901BLE.Close();
    }

    // Let the Bluetooth manager start searching for devices
    WitBluetoothManager bluetoothManager =
    WitBluetoothManagerHelper.GetWitBluetoothManager();
    bluetoothManager.OnDeviceFound += new
    WitBluetoothManager.OnDeviceFoundHalder(OnFoundDevice);
    bluetoothManager.OnDeviceStatu += new
    WitBluetoothManager.OnDeviceStatuHalder(OnDeviceStatu);
    bluetoothManager.StartScan();
}

/// <summary>
```

```
/// This method will be called back when a Bluetooth device is found
/// </summary>
/// <param name="macAddr"></param>
/// <param name="sName"></param>
/// <param name="dType"></param>
/// <param name="mType"></param>
private void OnFoundDevice(string macAddr, string sName, int dType, int mType)
{
    // If a Bluetooth device starting with WT is found
    if (sName != null && sName.Contains("WT"))
    {
        // If this device is newly found
        if (FoundDeviceDict.ContainsKey(macAddr) == false)
        {
            BWT901BLE bWT901BLE = new BWT901BLE();
            // Specify the connected Bluetooth MAC code
            bWT901BLE.SetMacAddr(macAddr);
            // Set the device name
            bWT901BLE.SetDeviceName(sName);
            FoundDeviceDict.Add(macAddr, bWT901BLE);
            // Open this device
            bWT901BLE.Open();
            bWT901BLE.OnRecord += BWT901BLE_OnRecord;
        }
    }
}
```

Close Search

To stop searching, call the `bluetoothManager.StopScan()` method.

```
/// <summary>
/// Stop searching
/// </summary>
/// <param name="sender"></param>
/// <param name="e"></param>
private void stopScanButton_Click(object sender, EventArgs e)
```

```
{  
// Let the Bluetooth manager stop searching  
WitBluetoothManager bluetoothManager =  
WitBluetoothManagerHelper.GetWitBluetoothManager();  
bluetoothManager.StopScan();  
}
```

Receiving sensor data

Get the data

The BWT901BLE object will automatically solve the sensor data and save it on itself. The sensor data can be obtained through the BWT901BLE.GetDeviceData() method. BWT901BLE.GetDeviceData() needs to pass in a key to obtain the sensor data. Please check the key you need to use in the example. The key is saved in the WitSensorKey class.

```
/// <summary>  
/// Get device data  
/// </summary>  
private string GetDeviceData(BWT901BLE BWT901BLE)  
{  
StringBuilder builder = new StringBuilder();  
builder.Append(BWT901BLE.GetDeviceName()).Append(" \n");  
// Acceleration  
builder.Append("AccX").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKey.  
AccX)).Append("g \t");  
builder.Append("  
AccY").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKey.AccY)).Append("g  
\t");  
builder.Append("AccZ").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKey.  
AccZ)).Append("g \n");  
// Angular velocity  
builder.Append("GyroX").Append  
(":").Append(BWT901BLE.GetDeviceData(WitSensorKey.AsX)).Append("°/s \t");  
builder.Append("GyroY").Append(":").Append(BWT901BLE.GetDeviceData
```

```
(WitSensorKey.AsY)).Append("°/s \t");
builder.Append("GyroZ").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKey
.AsZ)).Append("° /s \n");
// Angle
builder.Append("AngleX").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKe
y.AngleX)).Append("° \t");
builder.Append("AngleY").Append("
:").Append(BWT901BLE.GetDeviceData(WitSensorKey.AngleY)).Append("° \t");
builder.Append("AngleZ").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKe
y.AngleZ)).Append("° \n");
// Magnetic field
builder.Append("MagX").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKey.
HX)).Append("uT \t" );
builder.Append("MagY").Append(":").Append(BWT901BLE.GetDeviceData(WitSensorKey.
HY)).Append("uT \t");
builder.Append("MagZ").Append(":
").Append(BWT901BLE.GetDeviceData(WitSensorKey.HZ)).Append("uT \n");
// Version number
builder.Append("VersionNumber").Append(":").Append(BWT901BLE.GetDeviceData(
WitSensorKey.VersionNumber)).Append("\n");
return builder.ToString();
}
```

Recording Data

The sensor data can be obtained through the BWT901BLE object, but usually the host computer needs to record the sensor data. BWT901BLE has an OnRecord event that will notify you when to record data. The OnRecord event can be implemented when the device is turned on; then the data can be recorded by coordinating the BWT901BLE.GetDeviceData() method

```
/// <summary>
/// This method will be called back when a Bluetooth device is found
/// </summary>
/// <param name="macAddr"></param>
/// <param name="sName"></param>
```

```
/// <param name="dType"></param>
/// <param name="mType"></param>
private void OnFoundDevice(string macAddr, string sName, int dType, int mType)
{
    // If a Bluetooth device starting with WT is found
    if (sName != null && sName.Contains("WT"))
    {
        // If this device is newly found
        if (FoundDeviceDict.ContainsKey(macAddr) == false)
        {
            BWT901BLE bWT901BLE = new BWT901BLE();
            // Specify the Bluetooth MAC code for the connection
            bWT901BLE.SetMacAddr(macAddr);
            // Set the device name
            bWT901BLE.SetDeviceName(sName);
            FoundDeviceDict.Add(macAddr, bWT901BLE);
            // Open this device
            bWT901BLE.Open();
            bWT901BLE.OnRecord += BWT901BLE_OnRecord;
        }
    }
}

/// <summary>
/// This will be called when the sensor data is refreshed. You can record the data here
. /// </summary>
/// <param name="BWT901BLE"></param>
private void BWT901BLE_OnRecord(BWT901BLE BWT901BLE)
{
    string text = GetDeviceData(BWT901BLE);
    Debug.WriteLine(text);
}
```

Setting up the sensor

The sensor can be operated by BWT901BLE method



BWT901BLE.UnlockReg() Sends the unlock register command

BWT901BLE.AppliedCalibration() Sends an applied calibration command

BWT901BLE.StartFieldCalibration() Sends a command to start magnetic field calibration

BWT901BLE.EndFieldCalibration() Sends the command to end magnetic field calibration

BWT901BLE.SendProtocolData() Send other commands

Calibration

Calibrate the sensor by calling the BWT901BLE.AppliedCalibration() method

```
/// <summary>
/// Add calibration
/// </summary>
/// <param name="sender"></param>
/// <param name="e"></param>
private void appliedCalibrationButton_Click(object sender, EventArgs e)
{
    // All connected Bluetooth devices are calibrated
    for (int i = 0; i < FoundDeviceDict.Count; i++)
    {
        var keyValue = FoundDeviceDict.ElementAt(i);
        BWT901BLE bWT901BLE = keyValue.Value;

        if (bWT901BLE.IsOpen() == false)
        {
            return;
        }

        try
        {
            // Unlock the register and send the command
            bWT901BLE.UnlockReg();
            bWT901BLE.AppliedCalibration();
        }
    }
}
```



```
// The following two lines are equivalent to the above, and it is recommended to use the
above
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x69, 0x88, 0xb5 });
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x01, 0x01, 0x00 });
}
catch (Exception ex)
{
    MessageBox.Show(ex.Message);
}
}
}
```

Magnetic field calibration

Calibrate the sensor magnetic field by calling the
BWT901BLE.StartFieldCalibration() method and the
BWT901BLE.EndFieldCalibration() method

```
/// <summary>
/// Start magnetic field calibration
/// </summary>
/// <param name="sender"></param>
/// <param name="e"></param>
private void startFieldCalibrationButton_Click(object sender, EventArgs e)
{
    // Start magnetic field calibration for all connected Bluetooth devicesfor
    (int i = 0; i < FoundDeviceDict.Count; i++)
    {
        var keyValue = FoundDeviceDict.ElementAt(i);
        BWT901BLE bWT901BLE = keyValue.Value;

        if (bWT901BLE.IsOpen() == false)
        {
            return;
        }
        try
        {

```

```
// Unlock registers and send commands
bWT901BLE.UnlockReg();

bWT901BLE.StartFieldCalibration();

// The following two lines are equivalent to the above, it is recommended to use the above
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x69, 0x88, 0xb5 });
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x01, 0x07, 0x00 });
MessageBox.Show("Start magnetic field calibration. Please rotate around the sensor's XYZ axes once each. After the rotation, click [End magnetic field calibration]");
}
catch (Exception ex)
{
    MessageBox.Show(ex.Message);
}
}
}

/// <summary>
/// 未磁电开关
/// </summary>
/// <param name="sender"></param>
/// <param name="e"></param>
private void endFieldCalibrationButton_Click(object sender, EventArgs e)
{

    // End magnetic field calibration for all connected Bluetooth devices
    for (int i = 0; i < FoundDeviceDict.Count; i++)
    {
        var keyValue = FoundDeviceDict.ElementAt(i);
        BWT901BLE bWT901BLE = keyValue.Value;

        if (bWT901BLE.IsOpen() == false)
        {
            return;
        }
        try
        {
            // Unlock the register and send the command
            bWT901BLE.UnlockReg();
        }
    }
}
```

```
bWT901BLE.EndFieldCalibration();  
// The following two lines are equivalent to the above, and it is recommended to use the  
above  
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x69, 0x88, 0xb5 });  
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x01, 0x00, 0x00 });  
}  
catch (Exception ex)  
{  
    MessageBox.Show(ex.Message);  
}  
}  
}
```

More

For other operations, please refer to the sensor manual.

Read sensor registers

You can read the sensor registers using the BWT901BLE.SendReadReg() method or the BWT901BLE.SendProtocolData() method.

After sending the read command, the register value will be saved in BWT901BLE. You need to use BWT901BLE.GetDeviceData() to get the register data.

```
/// <summary>  
/// Read register 03  
/// </summary>  
/// <param name="sender"></param>  
/// <param name="e"></param>  
private void readReg03Button_Click(object sender, EventArgs e)  
{  
    string reg03Value = "";  
    // Read register 03 of all connected Bluetooth devicesfor  
(int i = 0; i < FoundDeviceDict.Count; i++)  
{
```

```

var keyValue = FoundDeviceDict.ElementAt(i);
BWT901BLE bWT901BLE = keyValue.Value;

if (bWT901BLE.IsOpen() == false)
{
return;
}
try
{
// Waiting timeint
waitTime = 3000;
// Send a read command and wait for the sensor to return data. If the data is not read, the
waitTime can be extended, or read several timesbWT901BLE.SendReadReg
(0x03, waitTime);

// The following line is equivalent to the above. It is recommended to use the above
//bWT901BLE.SendProtocolData(new byte[] { 0xff, 0xaa, 0x27, 0x03, 0x00 }, waitTime);

// Get the values of all connected Bluetooth devices
reg03Value += bWT901BLE.GetDeviceName() + "The value of register 03 is:" +
bWT901BLE.GetDeviceData("03") + "\r\n";
}
catch (Exception ex)
{
MessageBox.Show(ex.Message);
}
}
MessageBox.Show(reg03Value);
}

```

BWT901BLE API

method	illustrate	Parameter Introduction	Return Value

void SetMacAddr(string macAddr)	Set the Bluetooth address to open	macAddr: Bluetooth address	void
void SetDeviceName(string DeviceName)	Set the device name	DeviceName: device name	void
void Open()	Open the device	none	void
bool IsOpen()	Is the device turned on?	none	Returns whether it is open Open: true Close: false
void Close()	Turn off the device	none	void
void SendData(byte[] data, out byte[] returnData, bool isWaitReturn, int waitTime, int repetition)	Sending Data	data: data to be sent returnData: data returned by the sensor isWaitReturn: Whether the sensor needs to return data waitTime: Waiting time for the sensor to return data, in milliseconds, default	void

		is 100ms repetition: number of repetitions	
void SendProtocolData(byte[] data)	Sending data with protocol	data: data to be sent	void
void SendProtocolData(byte[] data, int waitTime)	Send data with protocol and specify waiting time	data: data to be sent waitTime: waiting time	void
void SendReadReg(byte reg, int waitTime)	Send a command to read the register	reg: command to be sent waitTime: waiting time	void
void UnlockReg()	Unlock Register	none	void
void SaveReg()	Save registers	none	void
void AppliedCalibration()	Calibration	none	void
void StartFieldCalibration()	Start magnetic field calibration	none	void
void EndFieldCalibration()	End magnetic field calibration	none	void
void SetReturnRate(byte rate)	Set the return rate	rate: The return rate to be set	void
string GetDeviceName()	Get device	none	Returns the

	name		device name
string GetDeviceData(string key)	Get Key value data	key: data key value	Return data value